

WHAT IS NET WORK PHYSICS

WHAT IS NET WORK PHYSICS

UNDERSTANDING NET WORK IN PHYSICS

WHAT IS NET WORK PHYSICS IS A FUNDAMENTAL CONCEPT THAT DESCRIBES THE TOTAL AMOUNT OF ENERGY TRANSFERRED TO OR FROM AN OBJECT BY ALL FORCES ACTING UPON IT. IT'S NOT JUST ABOUT ONE FORCE; IT'S THE COMBINED EFFECT OF EVERYTHING PUSHING OR PULLING. UNDERSTANDING NET WORK IS CRUCIAL FOR COMPREHENDING HOW OBJECTS MOVE, CHANGE THEIR VELOCITY, AND INTERACT WITHIN A PHYSICAL SYSTEM. THIS ARTICLE WILL DELVE DEEP INTO WHAT NET WORK IS, EXPLORE ITS RELATIONSHIP WITH ENERGY, EXAMINE HOW IT'S CALCULATED, AND HIGHLIGHT ITS SIGNIFICANCE ACROSS VARIOUS PHYSICS PRINCIPLES. WE WILL UNRAVEL THE NUANCES OF POSITIVE, NEGATIVE, AND ZERO NET WORK AND DISCUSS REAL-WORLD APPLICATIONS THAT SHOWCASE ITS POWER.

TABLE OF CONTENTS

UNDERSTANDING NET WORK IN PHYSICS
WHAT IS NET WORK? THE CORE CONCEPT
THE RELATIONSHIP BETWEEN NET WORK AND ENERGY
CALCULATING NET WORK: FORMULAS AND METHODS
TYPES OF NET WORK: POSITIVE, NEGATIVE, AND ZERO
FACTORS INFLUENCING NET WORK
REAL-WORLD APPLICATIONS OF NET WORK
THE WORK-ENERGY THEOREM: A POWERFUL CONNECTION
CONCLUSION

WHAT IS NET WORK? THE CORE CONCEPT

NET WORK, IN THE REALM OF PHYSICS, REPRESENTS THE SCALAR SUM OF THE WORK DONE BY ALL INDIVIDUAL FORCES ACTING ON A SYSTEM OR AN OBJECT. IMAGINE PUSHING A BOX ACROSS THE FLOOR. THERE'S THE FORCE YOU APPLY, THE FRICTION FROM THE FLOOR, AND POSSIBLY THE FORCE OF GRAVITY PULLING IT DOWN AND THE NORMAL FORCE PUSHING IT UP. NET WORK CONSIDERS THE CONTRIBUTION OF EACH OF THESE FORCES TO THE OBJECT'S DISPLACEMENT. IT'S A MEASURE OF THE TOTAL ENERGY TRANSFER RESULTING FROM THE COMBINED ACTION OF THESE FORCES. IF THE NET WORK DONE ON AN OBJECT IS POSITIVE, IT MEANS ENERGY HAS BEEN ADDED TO THE OBJECT, TYPICALLY IN THE FORM OF KINETIC ENERGY. CONVERSELY, IF THE NET WORK IS NEGATIVE, ENERGY HAS BEEN REMOVED. WHEN THE NET WORK IS ZERO, THERE'S NO OVERALL CHANGE IN THE OBJECT'S KINETIC ENERGY, EVEN IF INDIVIDUAL FORCES HAVE DONE WORK. THIS CONCEPT IS FOUNDATIONAL FOR UNDERSTANDING MOTION AND ENERGY TRANSFORMATIONS.

DEFINING WORK DONE BY A SINGLE FORCE

BEFORE GRASPING NET WORK, IT'S ESSENTIAL TO UNDERSTAND WORK DONE BY A SINGLE FORCE. IN PHYSICS, WORK IS PERFORMED WHEN A FORCE CAUSES AN OBJECT TO MOVE OVER A DISTANCE. MATHEMATICALLY, THE WORK (W) DONE BY A CONSTANT FORCE (F) IS GIVEN BY THE PRODUCT OF THE FORCE'S MAGNITUDE AND THE DISPLACEMENT (d) IN THE DIRECTION OF THE FORCE: $W = F d \cos(\theta)$, WHERE θ IS THE ANGLE BETWEEN THE FORCE VECTOR AND THE DISPLACEMENT VECTOR. IF THE FORCE IS APPLIED IN THE SAME DIRECTION AS THE DISPLACEMENT, θ IS 0 DEGREES, AND $\cos(0) = 1$, SO $W = F d$. IF THE FORCE IS PERPENDICULAR TO THE DISPLACEMENT, θ IS 90 DEGREES, AND $\cos(90) = 0$, MEANING NO WORK IS DONE.

THE SUMMATION OF INDIVIDUAL WORK CONTRIBUTIONS

NET WORK, THEREFORE, IS THE ALGEBRAIC SUM OF THE WORK DONE BY EACH FORCE ACTING ON THE OBJECT. IF WE HAVE FORCES F_1, F_2, F_3 , AND SO ON, ACTING ON AN OBJECT THAT UNDERGOES A DISPLACEMENT, THE NET WORK (W_{NET}) IS CALCULATED AS: $W_{\text{NET}} = W_1 + W_2 + W_3 + \dots$. EACH W_i REPRESENTS THE WORK DONE BY THE INDIVIDUAL FORCE F_i . THIS SUMMATION IS CRUCIAL BECAUSE IT ALLOWS US TO DETERMINE THE OVERALL EFFECT OF ALL FORCES, WHICH ULTIMATELY DICTATES THE CHANGE IN THE OBJECT'S ENERGY STATE. FOR INSTANCE, IF ONE FORCE DOES POSITIVE WORK AND ANOTHER DOES NEGATIVE WORK, THEIR CONTRIBUTIONS CAN CANCEL EACH OTHER OUT, LEADING TO ZERO NET WORK.

THE RELATIONSHIP BETWEEN NET WORK AND ENERGY

THE CONCEPT OF NET WORK IS INTIMATELY INTERTWINED WITH ENERGY, PARTICULARLY KINETIC ENERGY. THE MOST PROFOUND CONNECTION IS ARTICULATED BY THE WORK-ENERGY THEOREM, WHICH STATES THAT THE NET WORK DONE ON AN OBJECT IS EQUAL TO THE CHANGE IN ITS KINETIC ENERGY. THIS THEOREM PROVIDES A POWERFUL TOOL FOR ANALYZING MOTION WITHOUT NEEDING TO EXPLICITLY CALCULATE ACCELERATIONS OR INDIVIDUAL FORCES. ESSENTIALLY, NET WORK IS THE MECHANISM BY WHICH ENERGY IS TRANSFERRED INTO OR OUT OF AN OBJECT'S KINETIC ENERGY.

KINETIC ENERGY: THE ENERGY OF MOTION

KINETIC ENERGY (KE) IS THE ENERGY AN OBJECT POSSESSES DUE TO ITS MOTION. IT IS DEFINED AS $KE = (1/2) m v^2$, WHERE ' m ' IS THE MASS OF THE OBJECT AND ' v ' IS ITS VELOCITY. AN OBJECT MOVING FASTER HAS MORE KINETIC ENERGY THAN THE SAME OBJECT MOVING SLOWER. WHEN NET WORK IS DONE ON AN OBJECT, IT DIRECTLY AFFECTS ITS KINETIC ENERGY. IF POSITIVE NET WORK IS PERFORMED, THE OBJECT GAINS KINETIC ENERGY, MEANING ITS SPEED INCREASES. IF NEGATIVE NET WORK IS DONE, THE OBJECT LOSES KINETIC ENERGY, AND ITS SPEED DECREASES.

ENERGY TRANSFORMATION AND CONSERVATION

NET WORK ALSO PLAYS A ROLE IN BROADER ENERGY TRANSFORMATIONS. WHILE THE WORK-ENERGY THEOREM SPECIFICALLY LINKS NET WORK TO KINETIC ENERGY, THE PRINCIPLE OF CONSERVATION OF ENERGY EXTENDS THIS. THE WORK DONE BY NON-CONSERVATIVE FORCES (LIKE FRICTION) CAN BE CONVERTED INTO OTHER FORMS OF ENERGY, SUCH AS HEAT OR SOUND, LEADING TO A DECREASE IN MECHANICAL ENERGY. CONVERSELY, THE WORK DONE BY CONSERVATIVE FORCES (LIKE GRAVITY) CAN BE STORED AS POTENTIAL ENERGY. UNDERSTANDING NET WORK HELPS US TRACK THESE ENERGY TRANSFERS WITHIN A SYSTEM.

CALCULATING NET WORK: FORMULAS AND METHODS

CALCULATING NET WORK CAN BE APPROACHED IN SEVERAL WAYS, DEPENDING ON THE COMPLEXITY OF THE FORCES INVOLVED AND THE OBJECT'S MOTION. THE MOST STRAIGHTFORWARD METHOD INVOLVES SUMMING THE WORK DONE BY EACH INDIVIDUAL FORCE. ALTERNATIVELY, IF THE FORCES ARE CONSTANT AND ACTING IN A STRAIGHT LINE, IT SIMPLIFIES CONSIDERABLY. FOR MORE COMPLEX SCENARIOS, CALCULUS MIGHT BE REQUIRED.

SUMMING INDIVIDUAL WORK DONE

AS MENTIONED EARLIER, THE PRIMARY METHOD IS TO CALCULATE THE WORK DONE BY EACH FORCE ACTING ON THE OBJECT AND THEN SUM THESE VALUES. FOR A FORCE F APPLIED OVER A DISPLACEMENT d , WITH AN ANGLE θ BETWEEN THEM, THE WORK DONE BY THAT FORCE IS $W = F d \cos(\theta)$. IF MULTIPLE FORCES ARE ACTING, YOU CALCULATE W FOR EACH FORCE AND ADD THEM UP: $W_{\text{NET}} = W_1 + W_2 + W_3 + \dots$.

USING THE WORK-ENERGY THEOREM DIRECTLY

A MORE DIRECT APPROACH, ESPECIALLY WHEN YOU'RE INTERESTED IN THE CHANGE IN KINETIC ENERGY, IS TO USE THE WORK-ENERGY THEOREM: $W_{\text{NET}} = \Delta KE$. THE CHANGE IN KINETIC ENERGY IS CALCULATED AS THE FINAL KINETIC ENERGY MINUS THE INITIAL KINETIC ENERGY: $\Delta KE = KE_{\text{FINAL}} - KE_{\text{INITIAL}} = (1/2) m v_{\text{FINAL}}^2 - (1/2) m v_{\text{INITIAL}}^2$. THIS MEANS IF YOU KNOW THE INITIAL AND FINAL VELOCITIES OF AN OBJECT AND ITS MASS, YOU CAN DIRECTLY DETERMINE THE NET WORK DONE ON IT.

WORK DONE BY VARYING FORCES

WHEN FORCES ARE NOT CONSTANT OR THE PATH OF MOTION IS NOT A STRAIGHT LINE, CALCULATING WORK REQUIRES INTEGRATION. FOR A FORCE $F(x)$ ACTING ALONG THE X-AXIS AND CAUSING A DISPLACEMENT FROM x_1 TO x_2 , THE WORK DONE IS GIVEN BY THE INTEGRAL: $W = \int_{x_1}^{x_2} F(x) dx$. FOR A THREE-DIMENSIONAL SCENARIO, THIS BECOMES A LINE INTEGRAL OF THE FORCE VECTOR ALONG THE PATH OF DISPLACEMENT.

TYPES OF NET WORK: POSITIVE, NEGATIVE, AND ZERO

THE SIGN OF THE NET WORK DONE ON AN OBJECT PROVIDES IMMEDIATE INFORMATION ABOUT ITS ENERGY STATE. UNDERSTANDING THESE DISTINCTIONS IS KEY TO INTERPRETING PHYSICAL SCENARIOS CORRECTLY.

POSITIVE NET WORK

POSITIVE NET WORK OCCURS WHEN THE NET FORCE ACTING ON AN OBJECT HAS A COMPONENT IN THE DIRECTION OF ITS DISPLACEMENT. THIS MEANS THAT, OVERALL, ENERGY IS BEING TRANSFERRED INTO THE OBJECT. THE MOST COMMON CONSEQUENCE OF POSITIVE NET WORK IS AN INCREASE IN THE OBJECT'S KINETIC ENERGY, LEADING TO AN INCREASE IN ITS SPEED. THINK OF A SPRINTER ACCELERATING FROM THE STARTING BLOCKS; THE NET FORCE PUSHING THEM FORWARD DOES POSITIVE WORK, INCREASING THEIR SPEED.

NEGATIVE NET WORK

NEGATIVE NET WORK IS DONE WHEN THE NET FORCE ACTING ON AN OBJECT HAS A COMPONENT OPPOSITE TO THE DIRECTION OF ITS DISPLACEMENT. THIS IMPLIES THAT ENERGY IS BEING TRANSFERRED OUT OF THE OBJECT. CONSEQUENTLY, THE OBJECT'S KINETIC ENERGY DECREASES, AND ITS SPEED REDUCES. A CLASSIC EXAMPLE IS APPLYING THE BRAKES TO A CAR. THE BRAKING FORCE OPPOSES THE CAR'S MOTION, DOING NEGATIVE WORK AND CAUSING IT TO SLOW DOWN. FRICTION IS A COMMON FORCE THAT DOES NEGATIVE WORK.

ZERO NET WORK

ZERO NET WORK SIGNIFIES THAT THERE IS NO OVERALL CHANGE IN THE OBJECT'S KINETIC ENERGY. THIS CAN HAPPEN IN A FEW WAYS:

NO DISPLACEMENT: IF AN OBJECT IS ACTED UPON BY FORCES BUT DOES NOT MOVE ($d=0$), THEN NO WORK IS DONE BY ANY OF THE FORCES, RESULTING IN ZERO NET WORK.

CONSTANT VELOCITY: IF AN OBJECT IS MOVING AT A CONSTANT VELOCITY, ITS ACCELERATION IS ZERO. ACCORDING TO NEWTON'S SECOND LAW, THIS MEANS THE NET FORCE IS ZERO ($F_{\text{NET}} = 0$). IF THE NET FORCE IS ZERO, THE NET WORK DONE IS ALSO ZERO ($W_{\text{NET}} = F_{\text{NET}} d = 0$).

BALANCED FORCES: EVEN IF THERE IS DISPLACEMENT, IF THE TOTAL WORK DONE BY ALL FORCES SUMS TO ZERO, THE NET WORK IS ZERO. FOR INSTANCE, IF AN OBJECT IS LIFTED AT A CONSTANT VELOCITY, THE UPWARD FORCE APPLIED TO LIFT IT DOES

POSITIVE WORK, BUT GRAVITY DOES AN EQUAL AMOUNT OF NEGATIVE WORK. THE NET WORK IS ZERO, AND THE KINETIC ENERGY REMAINS CONSTANT.

FACTORS INFLUENCING NET WORK

SEVERAL FACTORS DIRECTLY INFLUENCE THE AMOUNT AND SIGN OF NET WORK DONE ON AN OBJECT. RECOGNIZING THESE ELEMENTS HELPS IN PREDICTING OR ANALYZING THE OUTCOME OF PHYSICAL INTERACTIONS.

THE MAGNITUDE AND DIRECTION OF FORCES

NATURALLY, THE STRONGER THE FORCES ACTING ON AN OBJECT, THE MORE POTENTIAL THERE IS FOR WORK TO BE DONE. EQUALLY IMPORTANT IS THE DIRECTION OF THESE FORCES RELATIVE TO THE OBJECT'S DISPLACEMENT. FORCES THAT ARE ALIGNED WITH THE DISPLACEMENT CONTRIBUTE TO WORK, WHILE THOSE PERPENDICULAR DO NOT. THE COMPONENT OF THE NET FORCE PARALLEL TO THE DISPLACEMENT IS WHAT ULTIMATELY DETERMINES THE NET WORK.

THE DISPLACEMENT OF THE OBJECT

WORK IS FUNDAMENTALLY LINKED TO DISPLACEMENT. IF AN OBJECT DOESN'T MOVE, NO WORK IS DONE, REGARDLESS OF THE FORCES ACTING UPON IT. THE GREATER THE DISPLACEMENT IN THE DIRECTION OF THE NET FORCE, THE GREATER THE NET WORK DONE.

THE ANGLE BETWEEN FORCE AND DISPLACEMENT

THE COSINE TERM IN THE WORK FORMULA ($W = F D \cos(\theta)$) HIGHLIGHTS THE CRITICAL ROLE OF THE ANGLE. WHEN $\theta = 0$ DEGREES (FORCE AND DISPLACEMENT ARE IN THE SAME DIRECTION), $\cos(\theta) = 1$, MAXIMIZING POSITIVE WORK. WHEN $\theta = 90$ DEGREES (FORCE AND DISPLACEMENT ARE PERPENDICULAR), $\cos(\theta) = 0$, RESULTING IN ZERO WORK. WHEN $\theta = 180$ DEGREES (FORCE AND DISPLACEMENT ARE IN OPPOSITE DIRECTIONS), $\cos(\theta) = -1$, RESULTING IN MAXIMUM NEGATIVE WORK.

REAL-WORLD APPLICATIONS OF NET WORK

THE CONCEPT OF NET WORK IS NOT CONFINED TO TEXTBOOKS; IT'S PRESENT IN COUNTLESS EVERYDAY PHENOMENA AND ENGINEERING APPLICATIONS.

AUTOMOTIVE ENGINEERING

WHEN A CAR ACCELERATES, THE ENGINE DOES POSITIVE WORK. HOWEVER, OPPOSING FORCES LIKE AIR RESISTANCE AND FRICTION FROM THE ROAD DO NEGATIVE WORK. THE NET WORK DONE ON THE CAR DETERMINES ITS CHANGE IN SPEED. SIMILARLY, WHEN A CAR BRAKES, THE BRAKING SYSTEM PERFORMS NEGATIVE NET WORK TO REDUCE ITS KINETIC ENERGY.

SPORTS AND ATHLETICS

CONSIDER A JAVELIN THROWER. THE ATHLETE APPLIES A FORCE OVER A DISTANCE, DOING POSITIVE WORK ON THE JAVELIN. AIR

RESISTANCE ALSO ACTS ON THE JAVELIN AS IT FLIES, DOING NEGATIVE WORK. THE NET WORK DONE ON THE JAVELIN DETERMINES ITS TRAJECTORY AND HOW FAR IT TRAVELS. IN WEIGHTLIFTING, WHEN A WEIGHTLIFTER LIFTS A BARBELL, THEY DO POSITIVE WORK AGAINST GRAVITY.

MECHANICAL SYSTEMS

IN ANY MACHINE INVOLVING MOVEMENT, NET WORK IS A CRITICAL CONSIDERATION. FOR EXAMPLE, AN ELEVATOR CABLE LIFTS A CAR. THE MOTOR DOES POSITIVE WORK, WHILE GRAVITY ACTS IN OPPOSITION. THE NET WORK DICTATES THE ELEVATOR'S ACCELERATION. UNDERSTANDING NET WORK ALLOWS ENGINEERS TO DESIGN SYSTEMS THAT ARE EFFICIENT AND PERFORM AS INTENDED.

THE WORK-ENERGY THEOREM: A POWERFUL CONNECTION

THE WORK-ENERGY THEOREM IS ARGUABLY THE MOST SIGNIFICANT OUTCOME DERIVED FROM THE CONCEPT OF NET WORK. IT ELEGANTLY LINKS THE MECHANICAL CAUSE (NET WORK) WITH ITS IMMEDIATE EFFECT (CHANGE IN KINETIC ENERGY). THIS THEOREM SIMPLIFIES MANY PROBLEMS IN CLASSICAL MECHANICS, ALLOWING US TO BYPASS THE NEED FOR DETAILED KINEMATIC ANALYSIS IN CERTAIN SITUATIONS.

DERIVATION AND SIGNIFICANCE

THE THEOREM CAN BE DERIVED FROM NEWTON'S SECOND LAW. FOR A CONSTANT FORCE F ACTING ON A MASS m OVER A DISPLACEMENT d , $F = ma$. THE WORK DONE IS $W = Fd$. SUBSTITUTING F , WE GET $W = (ma)d$. USING KINEMATIC EQUATIONS, WE KNOW THAT $v_f^2 = v_i^2 + 2ad$, WHICH CAN BE REARRANGED TO $d = (v_f^2 - v_i^2) / (2a)$. SUBSTITUTING THIS d INTO THE WORK EQUATION: $W = ma [(v_f^2 - v_i^2) / (2a)] = (1/2)m(v_f^2 - v_i^2) = (1/2)mv_f^2 - (1/2)mv_i^2 = KE_f - KE_i = \Delta KE$. THIS DEMONSTRATES THAT THE WORK DONE BY THE NET FORCE EQUALS THE CHANGE IN KINETIC ENERGY.

PRACTICAL PROBLEM SOLVING

THIS THEOREM IS INCREDIBLY USEFUL. IF YOU KNOW THE NET FORCE ACTING ON AN OBJECT AND THE DISPLACEMENT IT UNDERGOES, YOU CAN DIRECTLY CALCULATE THE CHANGE IN ITS SPEED WITHOUT FINDING ITS ACCELERATION FIRST. CONVERSELY, IF YOU KNOW THE INITIAL AND FINAL SPEEDS, YOU CAN DETERMINE THE TOTAL WORK DONE BY ALL FORCES.

CONCLUSION

IN ESSENCE, NET WORK IS THE OVERARCHING INDICATOR OF ENERGY TRANSFER DUE TO FORCES ACTING ON A MOVING OBJECT. IT'S THE SUM TOTAL OF ALL EFFORTS, WHETHER THEY HELP OR HINDER MOTION, THAT CONTRIBUTE TO A CHANGE IN AN OBJECT'S ENERGY. BY UNDERSTANDING NET WORK, WE UNLOCK A DEEPER COMPREHENSION OF HOW FORCES INFLUENCE MOTION AND ENERGY TRANSFORMATIONS, FROM THE SMALLEST PARTICLE TO THE LARGEST MECHANICAL SYSTEM. ITS PRINCIPLES UNDERPIN MANY OF THE PHYSICS WE ENCOUNTER DAILY AND ARE VITAL FOR SCIENTIFIC AND ENGINEERING ADVANCEMENTS.

FREQUENTLY ASKED QUESTIONS

Q: HOW IS NET WORK DIFFERENT FROM THE WORK DONE BY A SINGLE FORCE?

A: NET WORK IS THE SUM OF THE WORK DONE BY ALL INDIVIDUAL FORCES ACTING ON AN OBJECT, WHILE THE WORK DONE BY A SINGLE FORCE IS JUST THE CONTRIBUTION OF THAT ONE FORCE. NET WORK TELLS YOU THE OVERALL ENERGY TRANSFER, WHEREAS INDIVIDUAL WORK TELLS YOU THE ENERGY TRANSFER BY A SPECIFIC FORCE.

Q: CAN NET WORK BE ZERO EVEN IF FORCES ARE ACTING ON AN OBJECT?

A: YES, NET WORK CAN BE ZERO IF THE DISPLACEMENT IS ZERO, IF THE NET FORCE IS ZERO (MEANING FORCES ARE BALANCED), OR IF THE POSITIVE WORK DONE BY SOME FORCES IS EXACTLY CANCELED OUT BY THE NEGATIVE WORK DONE BY OTHER FORCES.

Q: WHAT HAPPENS TO AN OBJECT WHEN POSITIVE NET WORK IS DONE ON IT?

A: WHEN POSITIVE NET WORK IS DONE ON AN OBJECT, ITS KINETIC ENERGY INCREASES. THIS MEANS THE OBJECT SPEEDS UP.

Q: WHAT IS THE RELATIONSHIP BETWEEN NET WORK AND FRICTION?

A: FRICTION IS A FORCE THAT TYPICALLY OPPOSES MOTION, SO IT USUALLY DOES NEGATIVE WORK. IF FRICTION IS A SIGNIFICANT FORCE, IT WILL CONTRIBUTE NEGATIVELY TO THE NET WORK DONE, POTENTIALLY SLOWING DOWN OR STOPPING AN OBJECT.

Q: DOES NET WORK DEPEND ON THE PATH TAKEN BY AN OBJECT?

A: FOR NON-CONSERVATIVE FORCES LIKE FRICTION, THE NET WORK DONE CAN DEPEND ON THE PATH. HOWEVER, IF ONLY CONSERVATIVE FORCES ARE INVOLVED (LIKE GRAVITY OR SPRING FORCES), THE NET WORK DONE DEPENDS ONLY ON THE INITIAL AND FINAL POSITIONS, NOT THE PATH. THE WORK-ENERGY THEOREM, WHICH RELATES NET WORK TO THE CHANGE IN KINETIC ENERGY, HOLDS TRUE REGARDLESS OF WHETHER THE WORK IS PATH-DEPENDENT.

[What Is Net Work Physics](#)

What Is Net Work Physics

Related Articles

- [what is negative energy physics](#)
- [what is energy loss in physics](#)
- [what is cv in physics](#)

[Back to Home](#)